

TUTORIAL 04:


CREATE MY CROCO CLIM CONFIG

In this tutorial, we do all the steps to prepare our first CROCO configuration. We will connect to the super-computer LENGAU and run Matlab to create climatological CROCO input files using CROCO tools. We will then run our first simulation on the CHPC cluster.

STEP 1: Logging onto the Lengau HPC cluster and go into your CROCO working directory

→ From a terminal/konsole, execute the following instruction:

```
ssh -X login@lengau.chpc.ac.za
```

 Replace **login** with your corresponding account number.

→ Reserve one interactive processor to do the pre-processing steps (Step 4 from #TUTORIAL01):

```
[login@login2 ~]$ qsubi1  
[login@cnode0220 ~]$
```



→ Go into your **croco** directory (**lustre/croco**):

```
[login@cnode0220 ~]$ cd lustre/croco  
[login@cnode0220 croco]$
```

NODES

→ Go into your **Run_Clim** working directory. If it does not exist (or if you want to recreate your grid), repeat the Step 2 from #TUTORIAL02 (edit **create_config.bash** and execute it):

```
[login@cnode0220 ~]$ cd Run_Clim  
[login@cnode0220 Run_Clim]$  
[login@cnode0220 Run_Clim]$
```

OR

```
[login@cnode0220 ~]$ ./create_config.bash  
[login@cnode0220 ~]$ cd Run_Clim  
[login@cnode0220 Run_Clim]$
```

NODES

STEP 2: Creating CROCO input files for Run_Clim

→ It is done with **MATLAB** 

→ Launch **MATLAB** with the command **matlab -nodesktop** (or the alias **mat**):

```
[login@cnode0220 Run_Clim]$ matlab -nodesktop  
[login@cnode0220 Run_Clim]$
```

NODES

→ Execute the command **start** and open **crocotools_param.m** using the Matlab command **edit**:

```
>> start  
>> edit crocotools_param
```



↪ Activate the creation of graphics after each pre-processing step by changing **makeplot=0** to **makeplot=1** at line 131.

→ (Optional) Create your CROCO grid using the Matlab command **make_grid**:

```
>> make_grid  
>>
```



↪ Parameters for this script can be found in section 1 of **crocotools_param.m** ("1- Configuration parameters") at line 43.

↪ This script will create your horizontal/vertical grid (position of the grid point, size of the grid cells, bottom topography, land mask, etc...) using information from the global etopo2 data base. The grid will be stored in the NetCDF file **CROCO_FILES/croco_grd.nc**

→ Remember the size of your grid (**LLm0,MMm0**)

→ Create your CROCO surface forcing files:

```
>> make_forcing
>>
```

→ Parameters for this script can be found in section 3 of [crocotools_param.m](#) (“3- Surface forcing parameters”) at line 200.

→ This script will create your model surface forcing (surface wind stress, surface heat fluxes, surface freshwater flux), using data from the global COADS 2005 database. The surface forcing will be stored in the NetCDF file **CROCO_FILES/croco_frc.nc**

→ (Off Matlab) You can look at the COADS05 atlas:

```
[login@cnode0220 Run_Clim]$ cd ../../croco_tools/COADS05
[login@cnode0220 Topo]$ ncview precip.nc
```



```
>> make_bulk
>>
```

→ Parameters for this script can be found in section 3 of [crocotools_param.m](#) (“3- Surface forcing parameters”) at line 200.

→ This script will create your model surface forcing using bulk formulae: temperature at 2m, humidity at 2m, wind (u and v) at 10m and solar radiation, using data from the global COADS database. The surface bulk forcing will be stored in the NetCDF file **CROCO_FILES/croco_blk.nc**

```
>> make_QSCAT_clim
>>
```


→ Parameters for this script can be found in section 3 of [crocotools_param.m](#) (“3- Surface forcing parameters”) at line 200.

→ This script will extrapolate and interpolate surface data from QuickSCAT SCOW Climatology to get surface wind stress forcing. The surface forcing stress (variables sustr, svstr) will replace the one already stored in the NetCDF file **CROCO_FILES/croco_frc.nc** (estimated from COADS, see [make_forcing](#)).

→ (Off Matlab) You can look at the QuikSCAT SCOW climatological fields:

```
[login@cnode0220 Topo]$ cd ../QuikSCAT_clim
[login@cnode0220 QuikSCAT_clim]$ ncview roms_SCOW_*.nc
```



→ Create your CROCO initial and boundary conditions.  The following steps (make_clim, make_bry and make_ini) required to have run [make_forcing](#) first.

```
>> make_bry
>> make_ini
```

OR

```
>> make_clim
>>
```

→ Parameters for these scripts can be found in section 4 of [crocotools_param.m](#) (“4- Open boundaries and initial conditions parameters”) at line 233.

- Check your open boundary switches
- You can choose which data set you would like to use: CARS2009 or WOA2009

→ The scripts will create your model initial conditions and the boundary conditions (Temp, Salt, currents, SSH), using data from the global World Ocean Atlas (WOA2009) or CARS2009. The initial conditions will be stored in the NetCDF file **CROCO_FILES/croco_ini.nc**. The open boundary conditions will be stored in the NetCDF files **CROCO_FILES/croco_clm.nc** and/or **CROCO_FILES/croco_bry.nc**

→ (Off Matlab) You can look at the WOA2009 or CARS2009 climatologies:

```
[login@cnode0220 QuikSCAT_clim]$ cd ../WOA2009
[login@cnode0220 WOA2009]$ ncview temp_month.nc
```



→ **exit** Matab, you are finished with step 2.

```
>> exit
>>
```



→ You can inspect all your input files stored in CROCO_FILES using the **ncdump** or **ncview** tools:

```
[login@cnode0220 WOA2009]$ cd ../../croco/Run/CROCO_FILES/
[login@cnode0220 CROCO_FILES]$ ncdump -h croco_frc.nc
[login@cnode0220 CROCO_FILES]$ ncview croco_clm.nc
[login@cnode0220 Run_Clim]$ cd ..
```

NODES

STEP 3: Compiling CROCO model

→ You will use a compiler (ifort) to convert FORTRAN programs into an executable. For this you need to copy into your Run_Clim directory my **jobcomp_lengau** file:

```
cp /mnt/lustre/users/sillig/CROCO_TRAINING_Week1/3_Some_files/jobcomp_lengau .
```

→ You can check the differences between **jobcomp** and **jobcomp_lengau**:

```
[login@cnode0220 Run_Clim]$ diff jobcomp jobcomp_lengau
```

→ Edit the CROCO parameter file **param.h** using **vi** or **nedit**:

```
[login@cnode0220 Run_Clim]$ nedit param.h &
[login@cnode0220 Run_Clim]$
```

NODES

→ At the line corresponding to your configuration, fix **LLm0**, **MMm0** and **N** (line 182). If you create a new config, add the name of your configuration and set **LLm0**, **MMm0** and **N**, below line 180.

→ Check the parameters for the parallelisation (**NP_XI**, **NP_ETA**)

→ Edit the **cppdefs.h** file using **vi** or **nedit**:

```
[login@cnode0220 Run_Clim]$ nedit cppdefs.h &
[login@cnode0220 Run_Clim]$
```

NODES


→ At line 69, activate your config (ex : **#define BENGUELA_LR**).

→ Activate MPI parallelization at line 72 (**# define MPI**).

→ Define which of your boundaries are open or closed (line 86-89).

→ Activate the CPPKEYS for surface forcing choice (ex : **#define BULK_FLUX**).

→ Choose between bry or clm files for the open boundary conditions.

 You cannot activate both CPPKEYS: **CLIMATOLOGY** (line 243) and **FRC_BRY** (line 261)

→ Compile CROCO using the **jobcomp_lengau** script:

```
[login@cnode0220 Run_Clim]$ ./jobcomp_lengau
[login@cnode0220 Run_Clim]$
```

NODES


STEP 4: Running CROCO

→ To launch your simulation on the Lengau cluster using the PBS Pro job scheduler, you need to copy into your Run_Clim the **run_croco.pbs** file:

```
cp /mnt/lustre/users/sillig/CROCO_TRAINING_Week1/3_Some_files/run_croco.pbs .
```

→ You can check the differences between **run_croco.pbs** and **run_croco.bashrc**:

```
[login@cnode0220 Run_Clim]$ diff run_croco.pbs run_croco.bashrc
```

→ Check the PBS scheduler parameter and put your email address (not mine 

→ Check the path of your **Run_Clim** working directory.

→ Edit the CROCO parameter file **croco_inter.in** using **vi** or **nedit**:

```
[login@cnode0220 Run_Clim]$ nedit croco_inter.in &  
[login@cnode0220 Run_Clim]$
```

NODES

↪ Fix your grid parameters at line 8: THETA_S, THETA_B, Hc (m)

↪ Check the outputs requested in sections:

- primary_history_fields and primary_history_fields for instantaneous outputs
- primary_averages and primary_history_fields for averages

→ Edit the script **run_croco.pbs** using **vi** or **nedit**:

```
[login@cnode0220 Run_Clim]$ nedit run_croco.pbs &  
[login@cnode0220 Run_Clim]$
```

NODES

↪ Check the use configurable section. In particular, check out the time step (DT) and the parameters for the parallelisation (NBPROCS).

→ Launch your first simulation using the PBD command **qsub**:

```
[login@cnode0220 Run_Clim]$ qsub run_croco.pbs  
[login@cnode0220 Run_Clim]$
```

NODES

↪ Your simulation will soon start. You will receive an email.

↪ The model outputs will be stored in the directory: **./SCRATCH**



STEP 5: Visualising model outputs

→ This can be done with **MATLAB**

→ Launch **matlab -nodesktop** (or the alias **mat**) to use the crocotools diagnostics:

```
>> start  
>> edit croco_diags and complete the configurable part  
>> croco_diags  
>> plot_diags
```



→ Use the **croco_gui** to visualize your outputs:

```
>> croco_gui  
>>
```



↪ Have fun!

→ You can concatenate model outputs to visualize them easily in **croco_gui**:

```
[login@cnode0220 Run_Clim]$ cd SCRATCH  
[login@cnode0220 SCRATCH]$ nccat croco_avg_Y2M[1-9].nc  
croco_avg_Y2M1[0-2].nc croco_avg_Y2.nc
```

NODES

STEP 6: Exiting

→ When you are done, exit Matlab and logout from the super-computer:

```
[login@cnode0220 Run_Clim]$ exit  
logout  
qsub: job 4416950.sched01 completed  
[login@login2 ~]$ exit
```

